






Jig software installation manual ver1.00

SIE Inc. CS Dept.

Revision list

Rev.	Date	Discription	Drown by	Checked by	Approved by
1.00	2020/11/12	Release			

Purpose

- You need to install JIG Software (hereinafter referred to as Mapps) on the JIG PC for repair service.
- I explain that about other tools for using Mapps.

Equipment list


- Hardware
 - JIG PC (Windows 10 64bit)
 - Additional LAN Port
- Software
 - Mapps
 - (for SI-2) Apache & Visual Studio C++ 2017 Redistributable

Getting Mapps


- Download from Crossword
 - Same Unit Repair : DG-PS5-0051E-xx
 - Refurbish : DG-PS5-0021E-xx

Install Mapps on JIG PC

- Unzip Mapps file and run "UpdateMapps.bat".



Run



Install Apache on JIG PC for SI-2

- Download Visual Studio C++ 2017 Redistributable from the official site and install it.
- To run “HttpServerInstall.bat” of Apache as an **administrator**.
 - Crossword : DG-PS5-0031E-xx

Setting Additional LAN Port.



- IP address
 - 192.168.0.100
- Subnet Mask
 - 255.255.255.0

Select inspection process(1/2)

- In JIG01/2/3/4, some inspection process is able to change to each process by using a batch file. (CS dept will provide to be able to parallel run JIG02-04 Software.)
 - PI-2
 - DISI
 - SI-2
 - Commit
 - Drive Adjustment

Select inspection process(2/2)

- Run “C:/Mapps/JIG0*/Mapps/SwitchConfig.bat”, select process number that you change it.



EOF